



La création de Job



1) Dans « Home » cliquer sur « Backup Job » puis « Windows Computer » pour sauvegarder vos machines virtuelles Windows



2) Sélectionner le type de job que vous voulez faire, ainsi que le mode de traitement, soit par un agent soit par un serveur.

Add Computer

Host name or IP address:

Credentials:

Select existing or add new credentials

Add...

Manage accounts

OK Cancel

5) Indiquer le Nom de votre machine, ou son adresse IP

New Agent Backup Job

Backup Mode
Choose what data you want to back up from selected computers.

Job Mode

Name

Computers

Backup Mode

Storage

Guest Processing

Schedule

Summary

Entire computer
Back up entire computer image for fast recovery on any level. Deleted, temporary and page files are automatically excluded from the image to reduce the backup size.
 Include external USB drives

Volume level backup
Back up images of specified volumes, for example only data volumes. Deleted, temporary and page files are automatically excluded from the image to reduce the backup size.

File level backup (slower)
Back up selected files and directories only. This mode still produces an image-based backup, but only with protected file system objects included in the image.

< Previous Next > Finish Cancel

6) Sélectionner le mode de sauvegarde que vous voulez effectuer sur votre machine

New Agent Backup Job

Storage
Specify a backup repository to store the backup files produced by the backup job and customize advanced job settings if required.

Job Mode

Name

Computers

Backup Mode

Storage

Guest Processing

Schedule

Summary

Backup repository:
Default Backup Repository (Created by Veeam Backup) Map backup

11,1 GB free of 49,4 GB

Retention policy: 7 days Configure...

Keep certain full backups longer for archival purposes
GFS retention policy is not configured

Configure secondary destinations for this job
Copy backups produced by this job to another backup repository, or tape. We recommend to make at least one copy of your backups to a different storage device that is located off-site.

Advanced job settings include backup mode, compression and deduplication, block size, notification settings, automated post-job activity and other settings. Advanced...

< Previous **Next >** Finish Cancel

7) Cliquer sur « Next »

New Agent Backup Job

Schedule
Specify the scheduling options. If you do not set the schedule, the job will need to be controlled manually.

Job Mode

Name

Computers

Backup Mode

Storage

Guest Processing

Schedule

Summary

Run the job automatically

Daily at this time: 22:00 Everyday Days...

Monthly at this time: 22:00 Fourth samedi Months...

Periodically every: 1 Hours Schedule...

After this job: Server DOMOTECH (Created by WIN-TN3RL8L060M\Administrateur at 08/08/2016)

Automatic retry


Retry failed items processing: 3 times
Wait before each retry attempt for: 10 minutes

Backup window

Terminate job outside of the backup window Window...
Prevent long-running or accidentally started job from impacting your production infrastructure during the busy hours.

< Previous **Apply** Finish Cancel

8) Configurer la durée, la fréquence et la date de votre job



9) Votre Job est prêt, cliquer dessus et sélectionner « Active Full » pour une sauvegarde complète de votre machine

